Thunderbird - Checking your settings

1. Open Account Settings

- In Thunderbird, go to **Application Menu (≡) > Account Settings**.
- Alternatively, right-click your email account in the left pane and select **Settings**.

---

2. Update Server Settings

- In the left-hand menu, click on **Server Settings** under your account.
- Adjust as needed:
  - For IMAP:
    - **Server Name:** `imap.voice.net.au`
    - **Port:** `143 (STARTTLS), 993 (SSL/TLS)`
    - **Connection Security:** `STARTTLS for port 143)` or `SSL/TLS for port 993)`
    - **Authentication Method:** `Normal password`
    - **Username:** Your full email address (Eg `example.user@voice.net.au`)
  - For POP3:
    - **Server Name:** `pop.voice.net.au`
    - **Port:** `110 (STARTTLS), 995 (SSL/TLS)`
    - **Connection Security:** `STARTTLS for port 110)` or `SSL/TLS for port 995)`
    - **Authentication Method:** `Normal password`
    - **Username:** Your full email address (Eg `example.user@voice.net.au`)

---

3. Update Outgoing (SMTP) Settings


- Scroll down and click **Outgoing Server (SMTP)** at the bottom left.
- Select the correct SMTP server from the list, then click **Edit**.
- Adjust as needed:
  - **Server Name:** `smtp.voice.net.au`
  - **Port:** `587 (STARTTLS)` or `465 (SSL/TLS)`
  - **Connection Security:** `STARTTLS (Port 587)` or `SSL/TLS (Port 465)`
  - **Authentication Method:** `Normal password`
  - **Username:** Your full email address (Eg `example.user@voice.net.au`)


---

4. Save and Test

- Restart Thunderbird if it requests it and try sending/receiving mail to test.

Screenshot Examples


Local Folders
Account Settings
New Account
example.user@voice.net.au
Server Settings
Copies & Folders
Composition & Addressing
Junk Settings
Synchronisation & Storage
End-To-End Encryption
Return Receipts
Local Folders
Junk Settings
Disk Space
Outgoing Server (SMTP)
Server Settings
Server Type: IMAP Mail Server
Server Name: imap.voice.net.au
Port: 143
Default: 143
User Name: example.user@voice.net.au
Security Settings
Connection security: STARTTLS
Authentication method: Normal password
Server Settings
Check for new messages at startup
Check for new messages every 10 minutes
Allow immediate server notifications when new messages arrive
When I delete a message:
Move it to this folder: Deleted on example.user@voice.net.au
Just mark it as deleted
Remove it immediately
Advanced...
Message Storage
Clean up ("Expunge") Inbox on Exit
Empty Deleted folder on Exit
Message Store Type: File per folder (mbox)
Local Directory: C:\Users\Andrew Keynes\AppData\Roaming\thunderbird\Profiles\ckkxv5qc.default-release\Im
Browse...


New Account
example.user@voice.net.au
Server Settings
Copies & Folders
Composition & Addressing
Junk Settings
Synchronisation & Storage
End-To-End Encryption
Return Receipts
Local Folders
Junk Settings
Disk Space
Outgoing Server (SMTP)
Outgoing Server (SMTP) Settings
When managing your identities you can use a server from this list by selecting it as the Outgoing Server (SMTP), or you can use the default server from this list by selecting "Use Default Server".
example.user@voice.net.au - smtp.voice.net.au (Default)
Add...
Edit...
Remove
Details of selected server:
Description: <not specified>
Server Name: smtp.voice.net.au
Port: 587
User Name: example.user@voice.net.au
Authentication method: Normal password
Connection Security: STARTTLS
SMTP Server
Settings
Description:
Server Name: smtp.voice.net.au
Port: 587 Default:587
Security and Authentication
Connection security: STARTTLS
Authentication method: Normal password
User Name: example.user@voice.net.au
OK
Cancel